



User Instruction

U-Clone Master Mix for DNA Cloning and Mutagenesis

(Cat#: UC20 or UC100)

Important Note:

Store the U-Clone master mix at -20°C .




Key Features of U-Clone Master Kit:

- Seamless cloning within 15 min;
- Clone any insert at any site of any vector;
- Clone single, or multiple fragments, or mutagenesis at once;
- Add any adaptor, linker and tag in insert;
- No ligase and dephosphatase;
- No more than five colonies pick-up.

How U-Clone Works

The 2x U-Clone master mix contains a proprietary blend of enzymes that direct the assembly of DNA fragments with homology ends and further extend with the highest accuracy so far under cozy condition. A brief procedure was outline in chart below.


U-Clone Master kit is also suitable for DNA mutagenesis, including point mutation, insertion and deletion mutation, through multiple pair primers and multiple fragment assembly.





Preparation of insert and vector

1. **Linearize vector:** vector would be digested with your desired restrict enzymes and then the linearized vector would be purified.
2. **PCR the target gene:** The key part for successful cloning your target DNA into linearized vector is to design appropriate PCR primers. Each primer contains three parts: at least 16 bp of homology with the end of the linearized vector; plus restrict enzyme sites; and at least 20 bp of the gene-specific sequence. The guidelines for primer designs are shown in the diagram below.



3. **Multiple DNA fragment cloning:** If multiple DNA fragments will be assembled, the joining sequence should be at least 20 bp of homology in each end. More U-Clone master mix and longer incubate time will need.
4. **Other:** The PCR fragments should be generated by high fidelity DNA polymerase. Clean PCR product ensures the successful cloning. The melting temperature (T_m) would be based on the gene-specific end of the primer, NOT the entire primer. Enzyme 1 and 2 can be the same or different one in the vector. Additional sequences can be included between vector and gene sequences.

Kit Components

- U-Clone Master Mix (2x) suitable for 20 or 100 reactions
- **Required Materials but Not Included:**
 - High-Fidelity DNA Polymerase and relative PCR materials (for generating PCR products).
 - 20 or 100 tubes of *E. coli* DH5a Super Efficiency Competent Cells
 - 5 or 25 ml of SOC medium



- LB (Luria-Bertani) plates with appropriate antibiotic.

Brief Protocol for U-Clone Reaction

1. A typical U-Clone reaction for vector with one insert fragment was described below. Generally, 50–100 ng of vectors with 2~4 fold of excess inserts will give a good transformation rate.
 - Optimized cloning efficiency will be obtained at 3~5× molar ratio of insert to vector. DNA insert and vector molar concentration is dependent on insert and vector's length and weight, respectively. The following formula: DNA pmols = $1.54 \times \text{ng} / (\text{PCR product or vector bps})$. e.g.
 - 100 ng of 3000 bp dsDNA is about 0.05 pmols.
 - 100 ng of 300 bp dsDNA is about 0.5 pmols.
 - If insert is less than 200 bps, more of inserts may need.
 - If more than two fragments will be assembled, additional U-Clone Master Mix may be required.
2. Linearize and purify vector DNA (20~100 ng in 2 μl). Usually, if 2 μg of vector DNA is digested, and eluted by 50 μl of EB buffer at final step when using Qiagen Gel Extraction kit or other kits, the DNA concentration would be 20~30 ng/ μl . Use 2 μl of this product per reaction. Note: Do not use the linearized vector after two months of storage, even though stored in -20°C .
3. Purify PCR product(s). Mostly, the purification step of PCR products is not necessary for DNA assembly. Adding PCR reaction directly to assembly system will give a similar result.
4. Mix the linearized vector (2 μl) and PCR product (1~8 μl) in a clean PCR tube, bring to 10 μl with water. All reaction should be set up on ice.
5. Add the above mixture to 10 μl of 2× U-Clone master mix, flick to mix it and then spin down briefly.



6. Set a program on Thermal Cycler (PCR machine) with step1= 50°C for 15 min (one fragment) to 60min (more than one fragment)→ step 2=4 °C/∞. Product can be frozen at - 20°C if desired.

U-Clone Transformation Protocol

1. Thaw chemically Super Efficiency Competent Cells on ice, aliquot 50 µl to 1.5ml micro-centrifuge tube.
2. Add 5-10 µl of the chilled U-Clone Reaction product to the competent cells. Mix gently by flicking the tube 4–5 times.
3. Place the mixture on ice for 30 minutes.
4. Heat shock on a 42°C heat block for 60 seconds.
5. Transfer tubes to ice for 2 minutes.
6. Add 250 µl of room-temperature SOC media to the tube.
7. Incubate the tube at 37°C for 60 minutes with shaking (250 rpm).
8. Spread 60 µl of the cells onto the antibiotic-selection plates.
 - **Option:** Spin at 3000 rpm for 1 min, remain 50-100 µl of supernatants to resuspend pellet and spread all on the plate.
9. Incubate overnight at 37°C.

Question and Troubleshooting

Please contact: info@genexp-llc.com

Limited Use Label License: Research Use Only, Not for use in diagnostic procedures

Limited Use License and Warranty

Use of the "Product" is subject to the following terms and conditions. Genxp LLC ("We") warrant that the Product meets the specifications described in this manual. If the terms and conditions are not acceptable, please return all components of Products with original receipt by the original buyer to Genxp LLC within 10 business days. This product is for internal research purposes only and is not for use in commercial applications of any kind, including, without limitation, quality control and commercial services such as reporting the results of purchaser's activities for a fee or other form of consideration. No right or license to resell this product or any of its components is conveyed expressly, by implication, or by estoppel. This Product should be used in accordance with the NIH guidelines developed for recombinant DNA and genetic research. Genxp LLC disclaims any and all responsibility for injury or damage which may be caused by the failure of the buyer or any other person to use the Product in accordance with the terms and conditions outlined herein. If you should have any questions or concerns about any of our products, please contact us at info@genexp-llc.com or 1-888-425-6866.